

**VERSION:** 1.0 **DATE:** 2001

**PATHOGEN:** Pseudomonas syringae pv. glycinea (syn: Pseudomonas amygdali pv. glycinea)

**HOST:** Soybean (Glycine max)

**COMMON NAME:** bacterial blight

METHOD: Sb 4.2 Ground bulk seed–Serological and pathogenicity confirmation (Alvarez et

al.,1995)(formerly Sb2.2)

**METHOD CLASS:** STANDARD (A)

**SAMPLE:** 5,000 seeds

### PROCEDURE:

- 1. Five subsamples of 1000 dry soybean seeds are grinded in a Stein Mill for 1 min, then added to 600 ml of sterile saline (0.85% NaCl) and the suspension placed on a rotary shaker for 2 hr at 25°C at 220 rpm.
- 2. Threefold serial dilutions are made from the suspension and 0.1 ml aliquots plated on King's B medium amended with cephalexin.
- 3. After incubation at 25°C for 2-3 days, presumptive colonies of P. s. glycinea, exhibiting a blue fluorescence under UV light (370 nm), are re-isolated onto KBC.
- 4. Presumptive colonies of each subsample are confirmed as P. s. glycinea by the following pathogenicity and slide agglutination tests.

## Pathogenicity

- 1. Pathogenicity is determined by inoculating 15-day-old, greenhouse-grown soybean seedlings (cvs. Oakland, Beeson, Acme, and Flambeau) by rubbing leaves with a sterile cotton swab dipped in an aqueous suspension of the presumptive colony (approximately 10<sup>5</sup> cfu/ml).
- 2. The seedlings are incubated in light for 48 hr at 90% relative humidity in a mist chamber at 25°C, then transferred to the greenhouse and observed for necrotic lesions on leaves 4-7 days after inoculation.

# Agglutination

- 1. Ten microliters of bacterial suspension of each colony ( $10^5$  cfu/ml) was mixed in polystyrene Micro ELISA plates (Dynatech Corp.) with 10  $\mu$ l of a 1:1,000 aqueous dilution of the antiserum obtained from A. Calzolari (Osservatorio Regionale per le Malattie delle Plante, Bologna, Italy).
- 2. The plates are agitated for 1 hr at 25°C on a rotary shaker at 220 rpm, and agglutination is determined under a stereoscopic microscope.

#### MEDIA:

King's B Medium

Diwater	1 liter
DI water	1 liter
Proteose peptone #3	20g
K <sub>2</sub> HPO <sub>4</sub>	2.5g
Glycerol	15ml
MgSO <sub>4</sub> * 7H <sub>2</sub> O	6g
Agar	20g

<sup>\*4</sup>ml cephalexin from the stock solution per liter applied after autoclaving. (Stock = 1g per 100ml water)

### **REFERENCES:**

Alvarez, E., Braun. E. J., and McGee, D.C. 1995. New assays for detection of Pseudomonas syringae pv. glycinea in soybean seed. Plant Dis. 79:12-14.